

Qomo Camera User Manual

PC lowest configuration request:

✓ CPU: 2.7GHz ×86 or ×64

✓ RAM: 2G or above

✓ ROM: 128G

✓ SYSTEM: Windows 7/8 /10

PC Recommended configuration:

✓ CPU: 3.2GHz×64


✓ RAM: 4G or above

✓ ROM: 500G

✓ SYSTEM: Windows 7/8/10



Qomo Camera interface



1. Menu:


Fullscreen: Software shows in the mode of full screen

Windows: Software shows in the mode of windows

About: Shows software information like version, or support

Exit: Close the foftware

Minimize: To minimize the software in the tool bar





2. Interactive tools



Move: To switch the mouse in selecting mode or move the shooting image

Annotation: Annotate in photos or writing in different color and thickness

Eraser: Clear part or full annotation

Capture: The photos captured will be saved in the files "CameraCapture".

You can open it by clicking "View files"

Screen: capture the whole screen

Region: capture regular part

Irregular: capture irregular area

Photograph: Take picture of the area shot by the document camera and saved in the files "CameraPhoto"

Record: Take video in AVI format. The video will last 3 minutes by default if you don't stop it. It will be saved in the files "CameraVideo".

Adjustment: Rotate image, zoom in/out image or self-adaption, freeze or unfreeze image

Camera: Adjust camera resolution to adapt your PC. The resolution is 1920*1080 by default.




3. Picture tools




View files: You can open the files of capture, photograph or video

Compare: Compare photos in two windows, or four windows, and click cancel to close the comparison.



Two windows comparison





Four windows comparison

